


[howto](#), [openvpn](#), [pfsense](#), [sitetosite](#), [vpn](#), [apu1c4](#), [pcengines](#)

simple site to site VPN with pfSense and OpenVPN

I just had to set up a simple site to site VPN between a site with a fixed IP (SITE-B) and a site with a dynamic IP (SITE-A). Both routers are running the 'Community Edition' of pfSense and are installed on PC Engines APU.1C4. I have followed the documentation at pfsense.org about how to [configure a Site To Site VPN with OpenVPN](#) to get the VPN up and running. Because some things aren't documented there I will put up my own HowTo here. Please do yourself a favour and read the [documentation at pfsense.org](#) first because it explains things in more detail than I will do here.



This HowTo will guide you through the setup of:


- An IPv4 'Site To Site VPN' with [OpenVPN](#) on the pfSense platform (2.3.4 at time of writing) as seen in the schema above with the specific settings for the PC Engines APU hardware platform.
- The client will autoconnect to the server and (in the event of disconnection) reconnect automatically.
- The authentication between the client and the server will happen automatically via pre-shared key.

Sources

- [pfsense.org - OpenVPN Site To Site](#)
- [The pfSense Book](#)

Configure the OpenVPN server on SITE-B router

- Navigate to 'VPN - OpenVPN'



- On the '**Servers**'-Tab click on the '**+ Add**'-button to add a new server

OpenVPN / Servers / Edit

Servers Clients Client Specific Overrides Wizards

General Information

Disabled Disable this server
Set this option to disable this server without removing it from the list.

Server mode Peer to Peer (Shared Key)

Protocol UDP

Device mode tun

Interface WAN

Local port 1194

Description Site_To_Site-SITE-A_SITE_B
A description may be entered here for administrative reference (not parsed).

Cryptographic Settings

Shared key Automatically generate a shared key

Encryption Algorithm AES-256-CBC (256 bit key, 128 bit block)

Auth digest algorithm RSA-SHA512 (512-bit)
Leave this set to SHA1 unless all clients are set to match. SHA1 is the default for OpenVPN.

Hardware Crypto No Hardware Crypto Acceleration

Tunnel Settings

IPv4 Tunnel Network 10.4.10.0/30
This is the IPv4 virtual network used for private communications between this server and client hosts expressed using CIDR (e.g. 10.0.8.0/24). The first network address will be assigned to the server virtual interface. The remaining network addresses can optionally be assigned to connecting clients (see Address Pool).

IPv6 Tunnel Network
This is the IPv6 virtual network used for private communications between this server and client hosts expressed using CIDR (e.g. fe80::/54). The first network address will be assigned to the server virtual interface. The remaining network addresses can optionally be assigned to connecting clients (see Address Pool).

IPv4 Remote network(s) 10.3.2.0/24
IPv4 networks that will be routed through the tunnel, so that a site-to-site VPN can be established without manually changing the routing tables. Expressed as a comma-separated list of one or more CIDR ranges. If this is a site-to-site VPN, enter the remote LAN/s here. May be left blank for non site-to-site VPN.

IPv6 Remote network(s)
These are the IPv6 networks that will be routed through the tunnel, so that a site-to-site VPN can be established without manually changing the routing tables. Expressed as a comma-separated list of one or more IP/PREFIX. If this is a site-to-site VPN, enter the remote LAN/s here. May be left blank for non site-to-site VPN.

Concurrent connections 1
Specify the maximum number of clients allowed to concurrently connect to this server.

Compression Enabled with Adaptive Compression
Compress tunnel packets using the LZO algorithm. Adaptive compression will dynamically disable compression for a period of time if OpenVPN detects that the data in the packets is not being compressed efficiently.

Type-of-Service Set the TOS IP header value of tunnel packets to match the encapsulated packet value.

Duplicate Connection Allow multiple concurrent connections from clients using the same Common Name.
(This is not generally recommended, but may be needed for some scenarios.)

Disable IPv6 Don't forward IPv6 traffic.

Advanced Configuration

Custom options
Enter any additional options to add to the OpenVPN server configuration here, separated by semicolon.
EXAMPLE: push "route 10.0.0.0 255.255.255.0"


Verbosity level default
Each level shows all info from the previous levels. Level 3 is recommended for a good summary of what's happening without being swamped by output.
None: Only fatal errors
Default through 4: Normal usage range
5: Output R and W characters to the console for each packet read and write. Uppercase is used for TCP/UDP packets and lowercase is used for TUN/TAP packets.
6-11: Debug info range

Save

pfSense is © 2004 - 2017 by Rubicon Communications, LLC (Netgate) All Rights Reserved. [View license](#)

- In the **'General Information'**-section:
 - **Disable this server:**
 - **Server mode:** Peer to Peer (Shared Key)
 - **Protocol:** UDP
 - **Device Mode:** tun
 - **Interface:** set it to whatever external interface you want to have your OpenVPN server listening on. In my case this is 'WAN'.
 - **Local port:** set it to the port you want the local OpenVPN server to listen on. Default is '1194'.
 - **Description:** Set an appropriate description e.g. 'Site_To_Site-SITE-A_SITE_B'
- In the **'Cryptographic Settings'**-section:
 - **Automatically generate a shared key:**
 - **Encryption Algorithm:** AES-256-CBC (256 bit key, 128 bit block)
 - **Auth digest algorithm:** RSA-SHA512 (512-bit)
 - **Hardware Crypto:** No Hardware Crypto Acceleration (this is PC Engines APU specific, if your hardware has crypto support - enable it)
- In the **'Tunnel Settings'**-Section:
 - **IPv4 Tunnel Network:** 10.4.10.0/30 (this a very small subnet with 2 useable IP addresses since there is only one server and one client)
 - **IPv6 Tunnel Network:** leave empty
 - **IPv4 Remote network(s):** 10.3.2.0/24 (this is a comma separated list for all the networks you want to connect to on the client side (SITE A))
 - **IPv6 Remote network(s):** leave empty
 - **Concurrent connections:** 1
 - **Compression:** Enabled with Adaptive Compression
 - **Type-of-Service:** Set the TOS IP header value of tunnel packets to match the encapsulated packet value
 - **Duplicate Connection:** Allow multiple concurrent connections from clients using the same Common Name
 - **Disable IPv6:** Don't forward IPv6 traffic
- In the **'Advanced Configuration'**-section:
 - **Custom options:** leave empty
 - **Verbosity Level:** default
- Click on **'Save'**-button

You should now be forwarded to the list with your configured OpenVPN servers under **'VPN - OpenVPN'** on the **'Servers'**-tab




- Click on the **'Edit'**-button (the pencil) and leave this window open because we will need to copy the **'Shared Key'** from this form

later.

Configure the OpenVPN client on SITE-A router

- Navigate to 'VPN - OpenVPN'



- Click the '**Clients**'-tab
- On the '**Clients**'-tab click the '+ **Add**'-button to add a new OpenVPN client

San e COMMUNITY EDITION System Interfaces Firewall Services VPN Status Diagnostics Gold pfsense.site-a.inside

VPN / OpenVPN / Clients / Edit

Servers Clients Client Specific Overrides Wizards

General Information

Disabled Disable this client
Set this option to disable this client without removing it from the list.

Server mode Peer to Peer (Shared Key)

Protocol UDP

Device mode tun

Interface WAN

Local port
Set this option to bind to a specific port. Leave this blank or enter 0 for a random dynamic port.

Server host or address site-b.site-b.de

Server port 1194

Proxy host or address

Proxy port

Proxy Auth. - Extra options none

Server hostname resolution Infinitely resolve server
Continuously attempt to resolve the server host name. Useful when communicating with a server that is not permanently connected to the Internet.

Description Site_To_Site-SITE-A_SITE_B
A description may be entered here for administrative reference (not parsed).

Cryptographic Settings

Peer Certificate Authority No Certificate Authorities defined. One may be created here: [System > Cert. Manager](#)

Peer Certificate Revocation list No Certificate Revocation Lists defined. One may be created here: [System > Cert. Manager > Certificate Revocation](#)

Auto generate Automatically generate a shared key

Shared Key

```
@f087bce79f20823f8fa85936a6a41c0
f499d8559ffad8eada7df32ac73913
7caf22ba1ed66fffc75b06fe03fbede
-----END OpenVPN Static key V3-----
```

Paste the shared key here

Encryption Algorithm AES-256-CBC (256 bit key, 128 bit block)

Auth digest algorithm RSA-SHA512 (512-bit)
Leave this set to SHA1 unless all clients are set to match. SHA1 is the default for OpenVPN.

Hardware Crypto No Hardware Crypto Acceleration

Tunnel Settings

IPv4 Tunnel Network 10.4.10.0/30
This is the IPv4 virtual network used for private communications between this client and the server expressed using CIDR (e.g. 10.0.8.0/24). The second network address will be assigned to the client virtual interface.

IPv6 Tunnel Network
This is the IPv6 virtual network used for private communications between this client and the server expressed using CIDR (e.g. fe80::/64). The second network address will be assigned to the client virtual interface.

IPv4 Remote network(s) 10.4.2.0/24
IPv4 networks that will be routed through the tunnel, so that a site-to-site VPN can be established without manually changing the routing tables. Expressed as a comma-separated list of one or more CIDR ranges. If this is a site-to-site VPN, enter the remote LAN's here. May be left blank for non site-to-site VPN.

IPv6 Remote network(s)
These are the IPv6 networks that will be routed through the tunnel, so that a site-to-site VPN can be established without manually changing the routing tables. Expressed as a comma-separated list of one or more IP/PREFIX. If this is a site-to-site VPN, enter the remote LAN's here. May be left blank for non site-to-site VPN.

Limit outgoing bandwidth Between 100 and 100,000,000 bytes/sec
Maximum outgoing bandwidth for this tunnel. Leave empty for no limit. The input value has to be something between 100 bytes/sec and 100 Mbytes/sec (entered as bytes per second).

Compression Enabled with Adaptive Compression
Compress tunnel packets using the LZ0 algorithm. Adaptive compression will dynamically disable compression for a period of time if OpenVPN detects that the data in the packets is not being compressed efficiently.

Type-of-Service Set the TOS IP header value of tunnel packets to match the encapsulated packet value.

Disable IPv6 Don't forward IPv6 traffic.

Don't pull routes Bars the server from adding routes to the client's routing table
This option still allows the server to set the TCP/IP properties of the client's TUN/TAP interface.

Don't add/remove routes Don't add or remove routes automatically
Pass routes to --route-upscript using environmental variables.

Advanced Configuration

Custom options
Enter any additional options to add to the OpenVPN client configuration here, separated by semicolon.

Verbosity level default
Each level shows all info from the previous levels. Level 3 is recommended for a good summary of what's happening without being swamped by output.
None: Only fatal errors
Default through 4: Normal usage range
5: Output R and W characters to the console for each packet read and write. Uppercase is used for TCP/UDP packets and lowercase is used for TUN/TAP packets.
6-11: Debug info range

pfSense is © 2004 - 2017 by Rubicon Communications, LLC (Netgate) All Rights Reserved. [View license](#)

- In the **'General Information'**-section:
 - Disable this client:
 - Server mode: Peer to Peer (Shared Key)
 - Protocol: UDP
 - Device mode: tun
 - Interface: Set to whatever external interface you want your OpenVPN client connect to the OpenVPN server at SITE-B. In my case this is 'WAN'.
 - Local port: leave empty
 - Server host or address: Set to the FQDN or IP address of the external SITE-B Interface. In this example it is 'site-b.site-b.de'.
 - Server port: Set to the same port you have set in the server setup at SITE-B. Default is '1194'.

Proxy host or address: leave empty

```
Proxy port: leave empty
Proxy Auth. – Extra options: none
Infinitely resolve server: ????
Description: Set an appropriate description e.g. 'Site_To_Site-SITE-A_SITE_B'
```

In the **'Cryptographic Settings'**-section:

```
Peer Certificate Authority: nothing to do here
Peer Certificate Revocation list: nothing to do here
```

```
Automatically generate a shared key:  – This will display a form field in which you can paste the key from the SITE-B server configuration.
```

Go back to SITE-B router. If you haven't left the window open, navigate to 'VPN - OpenVPN' and select the 'Servers'-tab, click on the 'Edit'-button (the pencil) next to the server you have created earlier

From:
<https://wiki.nanoscopic.de/> - nanoscopic wiki

Permanent link:
<https://wiki.nanoscopic.de/doku.php/pages/howtos/pfsense/simple-site-to-site-vpn-with-pfsense-and-openvpn?rev=1635767129>

Last update: 2021/11/01 11:45

